

PIMMS version 4.12b Users' Guide

K. Mukai

1 Introduction

PIMMS (Portable, Interactive, Multi-Mission Simulator) is intended as a versatile simulation tool for X-ray astronomers.

PIMMS uses one command `GO` for actual execution, while other commands are mostly used for setting up various parameters. This approach allows users to repeat similar calculations using a slightly different parameter.

PIMMS uses the following terms:

- Model: spectral model to be used. PIMMS contains a small set of simple spectral models, and others can be imported.
 - However, spectral simulation is not a strength of PIMMS — it does not output spectra as such, and it is unlikely that PIMMS can keep up with the multitude of models that are used for various types of objects. We recommend the use of XSPEC for a full spectral simulation.
- Instrument: in addition to the instrument for which simulation is to be done, you can also specify the **input** instrument for count rate calculations. This is used for calculating normalization of the model; rather than starting from the source flux in cgs unit, PIMMS can start from e.g., Einstein IPC count rate.

2 New in v4.12/v4.12a/v4.12b

Version 4.12b contains an updated set of effective area curves for Chandra instruments, suitable for Cycle 25 proposal preparation.

Version 4.12a contains a minor update in the output format for IXPE to prevent the possibility of uninformative lines when calculating the minimum exposure time needed to reach a desired level of MDP.

Version 4.12 newly supports the IXPE mission, providing, in addition to the count rate, the

estimated minimum detectable polarization (MDP) levels, or the exposure time necessary to reach the desired level of MDP.

Version 4.12 also fixes a standard-compliance bug in `pms_docrt.f`, which prevented it from compilation in the standard mode using certain modern compilers.

Version 4.12 also contains an updated set of effective area curves for Chandra instruments, suitable for Cycle 24 proposal preparation.

3 New in v4.11/v4.11a/4.11b

Version 4.11b contains an updated set of effective area curves for Chandra instruments, suitable for Cycle 23 proposal preparation.

Version 4.11a contains new effective area curves for INTEGRAL ISGRI, NICER, and XMM-Newton EPIC instruments. The update for ISGRI is the first since 2008 and changes in PIMMS outputs are notable. The new effective area curve for NICER is suitable for Cycle 3 proposers, although the differences are minor compared with the previous (Cycle 2) version. The update of the various EPIC effective area curves is intended for AO-20 proposers, but the differences from the previous (AO-19) versions are smaller than other the likely precision of PIMMS estimates.

Version 4.11 contains a new X-ray absorption model: an approximation of the `tbabs` model in `xspec`, with the "wilm" abundances. This model is now the default; should it be desirable, the new `ABSORPTION` command can be used to specify the old (Morrison and McCammon) absorption model. The two can result in predictions that are different by about 10% from each other.

Version 4.11 updates the instrument specific output for XMM-Newton pn. The changes reflect the fact that the project does not support the use of timing and burst options for EPIC pn with thin or medium filters any more; these modes continue to be supported with the thick filter, however.

4 New in v4.10/4.10a/4.10b

Version 4.10b contains an updated set of effective area curves for Chandra instruments, suitable for Cycle 22 proposal preparation.

Version 4.10a contains an updated set of effective area curves for XMM-Newton EPIC instruments, suitable for AO-19 proposal preparation.

Version 4.10 includes an update for NICER, suitable for Cycle 2 proposers. The changes in the effective area curve are minor; far more important is the updates in the broadband (now clearly

defined as 0.2-12 keV) background count rate; background rate in Version 4.9/4.9a was much higher, since it included contributions below 0.2 keV.

Version 4.10 also includes a set of effective area curves for Athena XIFU.

4.1 New in v4.9/4.9a

Version 4.9a contains an updated set of effective area curves for Chandra, appropriate for use in Cycle 21 proposals.

Version 4.9 contains an updated support for NICER, now including estimated background rates in several standard energy bands.

Version 4.9 also contains an updated set of effective area curves for XMM-Newton EPIC instruments, suitable for AO-18 proposal preparation. It also contains effective area curves for XMM-Newton Optical Monitor.

4.2 New in v4.8/4.8a/4.8b/4.8c/4.8d/4.8e/4.8f

Version 4.8f contains an updated set of effective area curves for Chandra, suitable for use for Cycle 20 proposals.

Version 4.8e contains a slightly updated set of effective area curves for XMM-Newton EPIC instruments suitable for AO-17 proposal preparation, although any differences with the previous version is extremely minor.

Version 4.8d contains an updated set of effective area curves for Chandra, suitable for use for Cycle 19 proposals.

Version 4.8c contains a slightly updated set of effective area curves for XMM-Newton EPIC instruments suitable for AO-16 proposal preparation, although any differences with the previous version is extremely minor.

Starting with Version 4.8b, PIMMS recognizes the latest Japanese X-ray astronomy satellite as *Hitomi*, updated from the pre-launch name of *ASTRO-H*. In addition, the support for the IXO project has been removed.

Version 4.8a contains a slightly updated set of effective area curves for Chandra, suitable for use for Cycle 18 proposals.

The pile-up formulae for the XMM-Newton EPIC instruments have been revised using the latest information from the instrument teams. This brings PIMMS in line with tools used at the XMM SOC.

It is released with new XMM-Newton EPIC effective area curves suitable for AO-15 proposal preparation, although any differences with the previous version is extremely minor.

It is also released with new ASTRO-H HXI effective area curves.

4.3 New in v4.7/4.7a/4.7b/4.7c/4.7d

Version 4.7d contains an updated, though still somewhat preliminary, effective area curve for the NICER mission.

Version 4.7c is released with a new set of Chandra effective area curves suitable for preparation of Cycle 17 proposals, and a new set of Suzaku XIS effective area curves suitable for preparation of AO-10 proposals. However, any differences with the respective previous versions are extremely minor.

Version 4.7b is released with new XMM-Newton EPIC effective area curves suitable for AO-14 proposal preparation, although any differences with the previous version are extremely minor.

Version 4.7a contains an updated effective area curve and associated information for NuSTAR, reflecting the post-launch understanding of the mission. Although documentations for version 4.7 (released 2014 March 5) claimed this update was made in that version, this was regrettably not the case due to a configuration management error. In version 4.7a, the new effective area curve is included and the upper limit of the instrument energy range was updated from 80 keV to 79 keV.

Version 4.7 newly includes effective area curves for MAXI SSC and GSC all-sky monitor instruments. It also newly includes support for the HEAO-1 A1 instrument, appropriate for a direct comparison with the HEAO-1 A1 X-ray Source Catalog. It also contains updated effective area curves for the Chandra instruments, appropriate for Cycle 16 proposals. Differences with Cycle 15 versions are minor.

The set of APEC model files have been re-generated using ATOMDB 2.0.2 using xspec version 12.8.1g on 2013 Dec 9-11, with the “solar” abundance values of Asplund et al. 2009. Previous APEC model files were based on ATOMDB 1.3.1 and Anders & Grevesse solar abundances.

4.4 New in v4.6/4.6a/4.6b

Version 4.6b contains updated effective area curves for the Chandra instruments that are suitable for Cycle 15 proposers, although differences with the Cycle 14 versions are minor. The array size for missions and instruments have also been expanded in Version 4.6b, although this only affects users who wish to add many extra missions/instruments to the standard installation.

Version 4.6a contains a minor update of Suzaku XIS effective area curves appropriate for AO-8 proposers.

Version 4.6 includes a preliminary effective area curve for the proposed NICER mission. It also includes a preliminary algorithm to estimate the exposure times necessary to achieve 3 and 5 sigma detections with ASTRO-H SGD, the accuracy of which is currently under investigation.

4.5 New in v4.5

Version 4.5 includes an updated set of effective area curves for Chandra. It also includes a minor bug fix to the module that creates the help file used by PIMMS.

4.6 New in v4.4

Version 4.4 includes the effective area curve and further mission-specific support for NuSTAR. It also includes the initial estimate of SXS pile-up for the ASTRO-H mission, along with updated effective area curves for all instruments. It also includes minor updates for the effective area curves for XMM-Newton and Suzaku.

4.7 New in v4.3

Version 4.3 includes a new mission-specific comments regarding Integral JEM-X: two units are operational since 2010 October, but PIMMS continues to provide count rate per unit of JEM-X.

4.8 New in v4.2/v4.2a

Version 4.2a includes a new set of Chandra effective area curves, suitable for AO-13 proposers. Of the various instrument configurations, the HRC-I effective area curves changed the most.

Version 4.2 includes a new set of Suzaku effective area curves, suitable for Cycle 6 proposers, and an accompanying update in the code to estimate detection limits for the HXD detectors. Also, references to count rates for point sources observed at the HXD nominal position have been removed, as this pointing position is no longer recommended.

4.9 New in v4.1/4.1a/4.1b

Version 4.1b includes an updated effective area curves for XMM (suitable for AO-10 proposals) and for IXO, and an updated version of `pms_slmdl.f` which conforms strictly to the Fortran standard. (One compiler flagged the older version as an error; if it compiled, it worked correctly.)

By the request of XMM-Newton project at ESA, PIMMS version 4.1 reverts to using a large extraction region and PATTERNS 0 through 12 (for MOS)/4 (pn) in calculating EPIC count

rates. Version 4.1 incorrectly stated that the PATTERNS used was 0–4 for both EPIC-MOS and EPIC-pn, which was corrected in Version 4.1a.

Version 4.1 includes preliminary effective area curves for ASTRO-H, the Japanese-US mission scheduled for launch in 2014.

Version 4.1 now reports energy/wavelength ranges with an increased number of digits.

4.10 New in v4.0

As of version 4.0, two new grids of models for collisionally excited thermal plasma (using mekal and APEC codes) are available. The expanded grid of Raymond-Smith plasma model that was available as an add-on to the previous distributions are now standard; the more limited grid that was the standard in V3.9k and earlier versions has now been retired. Of the three grids, APEC is now the default. To switch among the plasma models, version 4.0 introduce a new command, “PLASMA.” The syntax of the “MODEL” command has accordingly changed. The old model name, “raymond-smith” (or RS) is no longer recognized, to be replaced with “PLASMA”. The model component, plasma, requires 3 numerical parameters: temperature, abundance, and Nh, in that order. An optional string parameter to be placed after the temperature can be used to switch the units of temperature from keV (default) to logT.

Log files now contain command echos.

As of Version 4.0, the effective area curves for missions Constellation-X, XEUS, and Spectrum X-Gamma have been removed from PIMMS. Those for the International X-ray Observatory (IXO) have been added.

Version 4.0 includes updated effective area curves for the Chandra instruments, suitable for Cycle 12 proposers.

See Appendix B, “Older Updates,” for a log of additions and changes before v4.0.

5 Sample Sessions

These sample sessions (using PIMMS v4.0) are available as *.xco files in the ‘sample’ subdirectory of PIMMS.

Example 1. Estimating Chandra ACIS-I count rate

```
*** PIMMS version 4.11 ***  
2020 Feb 27th Release
```

```

    Reading mission directory, please wait
* Current model is BREMSSTRAHLUNG, kT= 10.0000 keV; NH = 1.000E+21
    <--- Use 'MODEL' command to change
        and 'PLASMA' command to switch among APEC/mekal/RS
* By default, input rate is taken to be
    Flux (      2.000-      10.000 keV) in ergs/cm/cm/s
    <--- Use 'FROM' command to change the default
* Simulation product will be
    Count rate in CHANDRA ACIS-I
    <--- Use 'INSTRUMENT' command to switch to another instrument
PIMMS > go 1 einstein ipc
* For thermal Bremsstrahlung model with kT= 10.0000 keV; NH = 1.000E+21
    and 1.000E+00 cps in EINSTEIN IPC
    (Internal model normalization = 5.602E-03)
* PIMMS predicts 2.977E+00 cps with CHANDRA ACIS-I
% Pileup estimate for ACIS:
    Pile-up is too high (21.4 %) at the fastest single-chip frame time (0.2 s)
    Consult the Chandra POG for mitigation methods
PIMMS > quit

```

In this example, the default spectral model is used to estimate the Chandra ACIS-I count rate (which happens to be the default). The only place where user did not use the default set-up was to specify conversion from Einstein IPC count rate. PIMMS not only reports the total ACIS-I count rate but also the pile-up fraction for such a source.

Example 2. Estimating XTE count rates I

```

*** PIMMS version 4.11 ***
    2020 Feb 27th Release
    Reading mission directory, please wait
* Current model is BREMSSTRAHLUNG, kT= 10.0000 keV; NH = 1.000E+21
    <--- Use 'MODEL' command to change
        and 'PLASMA' command to switch among APEC/mekal/RS
* By default, input rate is taken to be
    Flux (      2.000-      10.000 keV) in ergs/cm/cm/s
    <--- Use 'FROM' command to change the default
* Simulation product will be
    Count rate in CHANDRA ACIS-I
    <--- Use 'INSTRUMENT' command to switch to another instrument
PIMMS > from exosat me
PIMMS > inst xte pca
PIMMS > mo plasma 1 1.0 5e19
NOTE: This version of PIMMS has a grid of 59x 5 grid of APEC models
    from kT= 0.034 keV (logT= 5.60) to kT=27.250 keV (logT= 8.50)
    and abundances from 0.20 to 1.00

```

Selected temperature is 0.967 keV (log T is 7.05)
 and selected abundance is 1.0
 PIMMS > go 1
 * For PLASMA (APEC) model with
 kT= 0.9669keV (logT= 7.05), Abund=1.0; NH = 5.000E+19
 and 1.000E+00 cps in EXOSAT ME
 (Internal model normalization = 3.655E-02)
 * PIMMS predicts 2.441E-01 cps with XTE PCA
 (Count rate is per PCU)

%% With 3 PCUs operational:
 (Use these numbers in RPS)

PIMMS predicts 0.732 cps from the source plus 91.380 background cps
 5-sigma detection will be achieved in 4295.926s
 (but undetectable with 1% systematic uncertainties in bgd)

Results in the 6 canonical XTE PCA bands are:

Channels	Nominal E (keV)	Source (cps)	BGD (cps)	5-sigma detection (s)	(+1%)
0- 13	0.00- 6.14	0.695	10.56	582.266	(1376.175)
14- 17	6.14- 7.90	0.031	3.46	9.00E+04	(*****)
18- 23	7.90- 10.5	5.47E-03	4.56	3.82E+06	(*****)
24- 35	10.5- 15.8	3.74E-04	7.87	1.41E+09	(*****)
36- 49	15.8- 22.1	1.71E-06	8.90	7.62E+13	(*****)
50-249	22.1-116.0	3.00E-09	56.05	1.56E+20	(*****)

%% ...and with 2 PCUs operational:

PIMMS predicts 0.488 cps from the source plus 60.920 background cps
 5-sigma detection will be achieved in 6.44E+03s
 (but undetectable with 1% systematic uncertainties in bgd)

Results in the 6 canonical XTE PCA bands are:

Channels	Nominal E (keV)	Source (cps)	BGD (cps)	5-sigma detection (s)	(+1%)
0- 13	0.00- 6.14	0.463	7.04	873.398	(2064.263)
14- 17	6.14- 7.90	0.021	2.31	1.35E+05	(*****)
18- 23	7.90- 10.5	3.64E-03	3.04	5.73E+06	(*****)
24- 35	10.5- 15.8	2.49E-04	5.24	2.11E+09	(*****)
36- 49	15.8- 22.1	1.14E-06	5.93	1.14E+14	(*****)
50-249	22.1-116.0	2.00E-09	37.37	2.34E+20	(*****)

PIMMS > model plasma 1.0 1 1e20

NOTE: This version of PIMMS has a grid of 59x 5 grid of APEC models
 from kT= 0.034 keV (logT= 5.60) to kT=27.250 keV (logT= 8.50)

and abundances from 0.20 to 1.00
 Selected temperature is 0.967 keV (log T is 7.05)
 and selected abundance is 1.0
 PIMMS > plasma mekal
 Current model has been changed
 * Current model is PLASMA (mekal) with
 kT= 0.9669keV (logT= 7.05), Abund=1.0; NH = 1.000E+20
 PIMMS > go 1
 * For PLASMA (mekal) model with
 kT= 0.9669keV (logT= 7.05), Abund=1.0; NH = 1.000E+20
 and 1.000E+00 cps in EXOSAT ME
 (Internal model normalization = 3.307E-02)
 * PIMMS predicts 2.528E-01 cps with XTE PCA
 (Count rate is per PCU)

%%% With 3 PCUs operational:
 (Use these numbers in RPS)

PIMMS predicts 0.758 cps from the source plus 91.380 background cps
 5-sigma detection will be achieved in 4005.449s
 (but undetectable with 1% systematic uncertainties in bgd)

Results in the 6 canonical XTE PCA bands are:

Channels	Nominal E (keV)	Source (cps)	BGD (cps)	5-sigma detection (s)	(+1%)
0- 13	0.00- 6.14	0.721	10.56	541.893	(1166.980)
14- 17	6.14- 7.90	0.032	3.46	8.66E+04	(*****)
18- 23	7.90- 10.5	4.87E-03	4.56	4.81E+06	(*****)
24- 35	10.5- 15.8	2.76E-04	7.87	2.59E+09	(*****)
36- 49	15.8- 22.1	8.02E-07	8.90	3.46E+14	(*****)
50-249	22.1-116.0	7.71E-10	56.05	2.35E+21	(*****)

%%% ...and with 2 PCUs operational:

PIMMS predicts 0.506 cps from the source plus 60.920 background cps
 5-sigma detection will be achieved in 6.01E+03s
 (but undetectable with 1% systematic uncertainties in bgd)

Results in the 6 canonical XTE PCA bands are:

Channels	Nominal E (keV)	Source (cps)	BGD (cps)	5-sigma detection (s)	(+1%)
0- 13	0.00- 6.14	0.481	7.04	812.840	(1750.471)
14- 17	6.14- 7.90	0.021	2.31	1.30E+05	(*****)
18- 23	7.90- 10.5	3.25E-03	3.04	7.22E+06	(*****)
24- 35	10.5- 15.8	1.84E-04	5.24	3.89E+09	(*****)

```

36- 49  15.8- 22.1  5.35E-07  5.93 5.19E+14 (*****)
50-249  22.1-116.0  5.14E-10 37.37 3.53E+21 (*****)
PIMMS > quit

```

In this example, the user specified conversion from EXOSAT ME count rate to XTE PCA and used plasma models with two different absorbing columns, also switching from APEC (default) to mekal before the second run. Since PIMMS uses a grid of pre-calculated plasma models, the temperature of the actual model used does not exactly match the request. PIMMS provides instrument-specific information for the XTE PCA (source and background count rates, and 5σ detection times in the entire passband and in the 6 canonical PCA bands with 2 or 3 PCUs operational).

Example 3. Estimating XTE count rates II

```

*** PIMMS version 4.11 ***
    2020 Feb 27th Release
    Reading mission directory, please wait
* Current model is BREMSSTRAHLUNG, kT= 10.0000 keV; NH = 1.000E+21
    <--- Use 'MODEL' command to change
        and 'PLASMA' command to switch among APEC/mekal/RS
* By default, input rate is taken to be
    Flux (      2.000-      10.000 keV) in ergs/cm/cm/s
    <--- Use 'FROM' command to change the default
* Simulation product will be
    Count rate in CHANDRA ACIS-I
    <--- Use 'INSTRUMENT' command to switch to another instrument
PIMMS > from ginga lac both
PIMMS > mo pl 1.5 15 30 1e22
PIMMS > inst xte pca
PIMMS > go 500
* For power-law model with high-energy cut-off with
    Index = 1.50, Ecut 15.00 keV, E(e-folding) 30.00 keV; NH = 1.000E+22
    and 5.000E+02 cps in GINGA LAC BOTH
    (Internal model normalization = 1.950E-01)
* PIMMS predicts 1.434E+02 cps with XTE PCA
    (Count rate is per PCU)

%%%      With 3 PCUs operational:
        (Use these numbers in RPS)

PIMMS predicts 430.284 cps from the source plus 91.380 background cps
5-sigma detection will be achieved in 0.070s
(or in 0.070s with 1% systematic uncertainties in bgd)

```

Results in the 6 canonical XTE PCA bands are:

Channels	Nominal E (keV)	Source (cps)	BGD (cps)	5-sigma detection (s)	(+1%)
0- 13	0.00- 6.14	159.874	10.56	0.167 (0.167)
14- 17	6.14- 7.90	64.852	3.46	0.406 (0.406)
18- 23	7.90- 10.5	74.181	4.56	0.358 (0.358)
24- 35	10.5- 15.8	82.633	7.87	0.331 (0.331)
36- 49	15.8- 22.1	33.182	8.90	0.955 (0.956)
50-249	22.1-116.0	15.562	56.05	7.393 (7.641)

%% ...and with 2 PCUs operational:

PIMMS predicts 286.856 cps from the source plus 60.920 background cps
 5-sigma detection will be achieved in 0.106s
 (or in 0.106s with 1% systematic uncertainties in bgd)

Results in the 6 canonical XTE PCA bands are:

Channels	Nominal E (keV)	Source (cps)	BGD (cps)	5-sigma detection (s)	(+1%)
0- 13	0.00- 6.14	106.582	7.04	0.250 (0.250)
14- 17	6.14- 7.90	43.235	2.31	0.609 (0.609)
18- 23	7.90- 10.5	49.454	3.04	0.537 (0.537)
24- 35	10.5- 15.8	55.089	5.24	0.497 (0.497)
36- 49	15.8- 22.1	22.121	5.93	1.433 (1.433)
50-249	22.1-116.0	10.375	37.37	11.089 (11.461)

PIMMS > inst xte hexte def

PIMMS > go 500

* For power-law model with high-energy cut-off with
 Index = 1.50, Ecut 15.00 keV, E(e-folding) 30.00 keV; NH = 1.000E+22
 and 5.000E+02 cps in GINGA LAC BOTH
 (Internal model normalization = 1.950E-01)

* PIMMS predicts 1.789E+01 cps with XTE HEXTE DEFAULT
 (Source-only count rate in 1 cluster; BGD rate is 73.1 per cluster)

5-sigma detection will be achieved in 14.7s

Results in the 4 canonical XTE HEXTE bands are:
 (per HEXTE cluster)

Channels	Nominal E (keV)	Source (cps)	BGD (cps)	5-sigma detection (s)
5- 29	12- 30	13.6	11.86	5.6
30- 61	30- 62	3.6	17.93	86.4
62-125	62- 126	6.56E-01	21.94	3004.3
126-250	126- 250	1.35E-02	21.35	6.88E+06

(The default 16-s rocking cycle is assumed for detection time)

PIMMS > quit

In this case, a special version of the power law model (with high energy cut-off) is used, by specifying index, cut-off energy and e-folding energy, as well as N_h , on the command line. User then calculated PCA and HEXTE count rates for a 500 cps Ginga LAC source.

Example 4. Estimating ROSAT PSPC count rates

```

*** PIMMS version 4.11 ***
    2020 Feb 27th Release
    Reading mission directory, please wait
* Current model is BREMSSTRAHLUNG, kT= 10.0000 keV; NH = 1.000E+21
    <--- Use 'MODEL' command to change
        and 'PLASMA' command to switch among APEC/mekal/RS
* By default, input rate is taken to be
    Flux (      2.000-      10.000 keV) in ergs/cm/cm/s
    <--- Use 'FROM' command to change the default
* Simulation product will be
    Count rate in CHANDRA ACIS-I
    <--- Use 'INSTRUMENT' command to switch to another instrument
PIMMS > from flux ergs 0.1-4
PIMMS > mo plasma 6.65 logt 0.6 3e19
PIMMS > inst rosat pspc open
PIMMS > go 5e-12
* For PLASMA (APEC) model with
        kT= 0.3849keV (logT= 6.65), Abund=0.6; NH = 3.000E+19
    and a flux (      0.100-      4.000keV) of 5.000E-12 ergs/cm/cm/s
    (Internal model normalization = 3.798E-03)
* PIMMS predicts 7.389E-01 cps with ROSAT PSPC OPEN
PIMMS > inst rosat pspc r6r7
PIMMS > go 5e-12
* For PLASMA (APEC) model with
        kT= 0.3849keV (logT= 6.65), Abund=0.6; NH = 3.000E+19
    and a flux (      0.100-      4.000keV) of 5.000E-12 ergs/cm/cm/s
    (Internal model normalization = 3.798E-03)
* PIMMS predicts 1.207E-01 cps with ROSAT PSPC R6R7
PIMMS > quit

```

In this example, 0.6 Solar abundance, $\log T=6.65$ APEC model with an absorption of $3 \times 10^{19} \text{ cm}^{-2}$ is used to estimate ROSAT PSPC count rates (total and in a combination of the Snowden R bands) for a $5 \times 10^{-12} \text{ ergs cm}^{-2} \text{ s}^{-1}$ source.

6 Using multi-component models – 3 examples

6.1 A 2-temperature plasma model

```
*** PIMMS version 4.11 ***
    2020 Feb 27th Release
    Reading mission directory, please wait
* Current model is BREMSSTRAHLUNG, kT= 10.0000 keV; NH = 1.000E+21
    <--- Use 'MODEL' command to change
        and 'PLASMA' command to switch among APEC/mekal/RS
* By default, input rate is taken to be
    Flux (      2.000-      10.000 keV) in ergs/cm/cm/s
    <--- Use 'FROM' command to change the default
* Simulation product will be
    Count rate in CHANDRA ACIS-I
    <--- Use 'INSTRUMENT' command to switch to another instrument
PIMMS > mo plasma 6.6 logt 1.0 3e19 plasma 7.2 logt 1.0 3e19 0.5 1.0
PIMMS > output apec2t 0.1 4.0 0.002
PIMMS > inst rosat pspc open
PIMMS > from flux ergs 0.1-2.0 u
PIMMS > go 3e-11
* For PLASMA (APEC) model with
    kT= 0.3431keV (logT= 6.60), Abund=1.0; NH = 3.000E+19
+ PLASMA (APEC) model with
    kT= 1.3657keV (logT= 7.20), Abund=1.0; NH = 3.000E+19
    ( 0.5000 times component 1 at 1.0000 keV)
    and an unabsorbed flux ( 0.100- 2.000keV) of 3.000E-11 ergs/cm/cm/s
    (Internal model normalization = 1.474E-02)
* PIMMS predicts 3.987E+00 cps with ROSAT PSPC OPEN
PIMMS> quit
```

This first example illustrates the use of two-temperature plasma model. The absorption columns (to be specified explicitly for each component) are the same in this example. The second component has a flux at 1 keV which is 50% of the first component. Note, however, this is a tricky proposition for the line-rich plasma models. It is best to [check this via the output command](#), which allows the users to check the actual model spectrum.

6.2 A model with partial-covering absoerber

```
*** PIMMS version 4.11 ***
    2020 Feb 27th Release
    Reading mission directory, please wait
* Current model is BREMSSTRAHLUNG, kT= 10.0000 keV; NH = 1.000E+21
```

```

<--- Use 'MODEL' command to change
      and 'PLASMA' command to switch among APEC/mekal/RS
* By default, input rate is taken to be
Flux (      2.000-      10.000 keV) in ergs/cm/cm/s
<--- Use 'FROM' command to change the default
* Simulation product will be
Count rate in CHANDRA ACIS-I
<--- Use 'INSTRUMENT' command to switch to another instrument
PIMMS > mo brems 15 3e23 brems 15 1e20 0.1 10 ga 6.5 0.1 250
PIMMS > output partial 0.1 10.0 0.005
PIMMS > inst xmm pn thin
PIMMS > go 0.5 asca sis
* For thermal Bremsstrahlung model with kT= 15.0000 keV; NH = 3.000E+23
  + thermal Bremsstrahlung model with kT= 15.0000 keV; NH = 1.000E+20
    ( 0.1000 times component 1 at 10.0000 keV)
  + Gaussian model with E= 6.5000 keV; sigma= 0.1000 keV; NH = 3.000E+23
    (Eq.W=250.0000 eV)
and 5.000E-01 cps in ASCA SIS
%% Integration over the entire chip (not just in the source region) assumed
(Internal model normalization = 9.009E-03)
* PIMMS predicts 6.462E+00 cps with XMM PN THIN
for on-axis observation, PATTERN=0-4, before dead time correction
and assuming a 5 arcmin extraction radius enclosing ~100% of the PSF
(The count rate within a more reasonable point source extraction region
of ~15 arcsec radius would be roughly ~70% of this value)
WARNING: The pile-up estimate is approximate

% Pile-up and dead-time corrected count rates in 4 energy bands
using various allowed window options are:

Window    Pileup    Dead          Corrected Good Count Rates
Option    frac.     Time          0.1-0.4    0.4-1.0    1.0-2.5    2.5-10.0    Total

Full       7.883%    7.0%          0.5357     0.9250     1.0405     2.7705     5.5363
FullExtd   >10%     7.0%          0.4295     0.7417     0.8343     2.2216     4.4394 ?
Large      5.190%    9.0%          0.5395     0.9315     1.0479     2.7901     5.5756
Small      0.482%    29.0%         0.4418     0.7629     0.8582     2.2850     4.5662

% Timing and Burst options are now only available for pn with the thick filter

% Any pile-up predictions over 10% are highly uncertain

PIMMS> quit

```

This example shows how to set up a spectrum suffering from partial covering absorption. In addition, a Gaussian is added which has a different syntax: the three parameters are the line

energy (keV), the physical width (keV), and the equivalent width (eV). Absorbing column is assumed to be the same as the first component (it can be specified explicitly, as the third parameter before the equivalent width).

6.3 A redshifted example

```
*** PIMMS version 4.11 ***
    2020 Feb 27th Release
    Reading mission directory, please wait
* Current model is BREMSSTRAHLUNG, kT= 10.0000 keV; NH = 1.000E+21
    <--- Use 'MODEL' command to change
        and 'PLASMA' command to switch among APEC/mekal/RS
* By default, input rate is taken to be
    Flux (      2.000-      10.000 keV) in ergs/cm/cm/s
    <--- Use 'FROM' command to change the default
* Simulation product will be
    Count rate in CHANDRA ACIS-I
    <--- Use 'INSTRUMENT' command to switch to another instrument
PIMMS > mo pl 1.7 3e23 ga 6.4 0.2 150 plasma 1.2 1.0 0.0 1.0 2.5 z 0.01 8e19
NOTE: This version of PIMMS has a grid of 59x 5 grid of APEC models
    from kT= 0.034 keV (logT= 5.60) to kT=27.250 keV (logT= 8.50)
    and abundances from 0.20 to 1.00
    Selected temperature is 1.217 keV (log T is 7.15)
    and selected abundance is 1.0
PIMMS > output agn_sb 0.1 10.0 0.01
PIMMS > inst chandra acis-s
PIMMS > go 1e-11
* For power law model with photon index = 1.7000; NH = 3.000E+23
    + Gaussian model with E= 6.4000 keV; sigma= 0.2000 keV; NH = 3.000E+23
        (Eq.W=150.0000 eV)
    + PLASMA (APEC) model with
        kT= 1.2172keV (logT= 7.15), Abund=1.0; NH = 0.000E+00
        ( 1.0000 times component 1 at 2.5000 keV)
...redshifted with z= 0.0100 and a Galactic Nh= 8.000E+19
    and a flux (      2.000-      10.000keV) of 1.000E-11 ergs/cm/cm/s
    (Internal model normalization = 5.883E-03)
* PIMMS predicts 2.000E-01 cps with CHANDRA ACIS-S
% Pileup estimate for ACIS:
    Pile-up is generally tolerable (10.0 %) at a frame-time of 1.324 s
PIMMS > quit
```

In this example, the entire composite model is to be redshifted with $z=0.01$. Absorption specified with each component is taken to be intrinsic (i.e., also redshifted). Additionally, a Galactic (unredshifted) absorption is specified. For ‘unabsorbed’ flux, both intrinsic and Galactic absorption will temporarily be set to 0.

7 Comments on extended sources

PIMMS is written primarily for point sources. To simulate the count rate for an extended source, estimate the total counts/flux within the field of view of the target instrument and use that as the input to the “GO” command.

8 Missions

PIMMS reads the list of missions from a file called “pms_mssn.lst” in the data directory. It then looks, for each mission (i.e., satellite), detector and “filter” combination, the appropriate calibration files for the effective area etc. Since this is a run-time process, the following items may not exactly correspond to what you see. For a listing of what is currently available, use the DIRECTORY command.

For active and near-future missions, we provide the latest effective area curves with PIMMS for proposal preparation purposes. If the effective area changes in-orbit, count rate to flux conversion factor for actual observations is time-dependent, which PIMMS is currently not well equipped to handle.

8.1 ASCA

The Japanese X-ray satellite *ASCA* had 4 co-aligned telescopes, each having an effective area of $\sim 250 \text{ cm}^2$ at 1 keV; there were two GIS (imaging gas scintillation proportional counters) and two SIS (Solid-state Imaging Spectrometer, X-ray CCDs) detectors. Count rates are given for a single GIS or a single SIS, as appropriate.

8.2 Athena

Athena (Advanced Telescope for High ENergy Astrophysics) is an ESA “Cosmic Vision” L(arge)-class mission, to be launched in the early 2030s. See <https://www.the-athena-x-ray-observatory.eu/> for further details of the mission.

Version 4.10 of PIMMS contains effective area curves for the proposed X-IFU (X-ray Integral Field Unit) instrument produced in late 2018, taken from http://x-ifu-resources.irap.omp.eu/PUBLIC/RESPONSES/CC_CONFIGURATION/ Since this is a high spectral resolution instrument, PIMMS should be used only to judge whether a spectral simulation is worthwhile, and if so, to provide the initial guess as to the likely exposure time needed. Note also that PIMMS assumes 100% throughput in estimating the count rates. The actual throughput will be less in a count-rate dependent manner.

8.3 BBXRT

BBXRT is flown on the Shuttle with the ASTRO payload in December 1990. The effective area curve is that for pixel A0.

8.4 CGRO

The Compton Gamma Ray Observatory OSSE instrument is now available as in PIMMS, primarily as an aid in Integral observation planning.

8.5 Chandra

The Chandra X-ray Observatory was formerly known as AXAF; starting with v2.7, the mission name in PIMMS has been changed to Chandra.

This version of PIMMS includes the Chandra instrument effective area curves appropriate for Cycle 25 proposers, as provided by the Chandra X-ray Observatory Center (<http://cxc.harvard.edu/>), where the details of the instruments can be found. Older versions of the effective area curves are available by request.

All effective areas assume an on-axis observation.

The 4 CCDs of the Chandra CCD Imaging Spectrometer Imaging array (ACIS-I) cover 17 by 17 arcmin of sky with 0.5 arcsec square pixels. PIMMS calculates the on-axis count rate uncorrected for pile-up.

Two of the 6 ACIS-S CCDs are back-illuminated (BI), to improve the low energy effective areas. For imaging with ACIS-S, the observer will thus have the choice of FI/BI. Since the FI chips have a performance identical to that of the ACIS-I chips, only the BI chip option is separately available in PIMMS.

High Resolution Camera covers a larger area of the sky with smaller pixels.

ACIS-S will be the normal readout instrument for HETG (High Energy Transmission Grating) spectra. The curves use the flight instrument chip layout of 4 FI and 2 BI chips. PIMMS will provide count rates for both grating subsets (MEG and HEG) separately, or for the combination. A single observation provides both spectra simultaneously in a cross-shaped orientation. Since the energy response and spectral resolution of the two grating assemblies differ, separation of the output may be important for some users. In all cases the output is for isolated first order. The energy resolution of the ACIS instrument will allow the user to separate this from the higher order light. See the Proposers' Observatory Guide for more information. Count rate in the zeroth order image can also be calculated.

HRC-S is the normal readout instrument for LETG (Low Energy Transmission Grating) spectra. PIMMS currently allows determination of the count rates in the 0th order image; 1st order spectrum; and the higher orders; through the "normal" part of the UV/Ion shield. NOTE in practice, due to the lack of energy resolution of the HRC, isolation of the first order signal will require a combination of "normal" and "low-energy reject" mode observations which are likely to take roughly twice as long as the estimate provided by PIMMS. An alternative is to use the High Energy Suppression Filter (HESF) which effectively isolates first order from 0.05-0.44 keV.

LETG data can also be read out with the ACIS-S detectors; 0th and 1st order count rates for this combination can also be estimated with PIMMS.

Observations of bright sources with ACIS are limited by photon pileups (see Proposers' Observatory Guide). This version of PIMMS includes a pileup estimate (based on the separate 'pileup' tool written at CXC). This feature will provide you with an estimate of the degree of pile-up for ACIS imaging mode observations (ACIS-I, ACIS-S, LETG-ACIS-I ORDER0, LETG-ACIS-S ORDER0, HETG-ACIS-I ORDER0, and HETG-ACIS-S ORDER0).

Note that this is valid only for point source observations on-axis.

Pile-up effect can be mitigated by placing the source off-axis — the inferior PSF will spread the photons over many pixels. Quantitative analysis of this is not yet available in PIMMS. The other principal method of altering the frame time can be evaluated by PIMMS. For this purpose, the 'go' command of PIMMS for ACIS-I and ACIS-S-BI allows an optional numerical parameter. If given, it will be taken as the frame time (allowed range: 0.2–3.2 s), and gives the pile-up fraction accordingly. If absent, PIMMS will attempt to estimate the frame time at which the pile-up fraction is 10% (which is the rule-of-thumb number above which you will have a severe problem). For the 0th order images, the default frame time of 3.2 s is assumed.

8.6 EINSTEIN

Currently PIMMS only have IPC and MPC effective area curves.

8.7 EUVE

PIMMS currently has the effective area curves for the three channels of the spectrometer, which is used by GOs for pointed observations. Detectors are SW (70–190Å), MW (140–480Å) and LW (280–750Å)

8.8 EXOSAT

For the Low Energy telescopes, only the LE1/CMA effective area data are kept within PIMMS. Specify filter OPEN, LX3, LX4, ALP, or BRN. The ME effective area is for a half-array; GSPC

area is also available.

8.9 Ginga

Ginga is the 3rd Japanese X-ray astronomy satellite, which carried the LAC (Large Area Counter) array with an effective area of $\sim 4000 \text{ cm}^2$. Count rate can be calculated for TOP layer of the detector only or BOTH.

8.10 HEAO-1

PIMMS currently contains supports for A1 and A4 LED instruments.

The PIMMS set-up for the A4 LED instrument is meant to make it straightforward to use the Levine et al (1984, ApJS 54, 281) catalog for XTE proposals. As an input, use the A+B+C combined count rate; as an output, A+B+C rate as well as the individual rate in the four bands (A through D) are given. One suggested use is to specify “HEAO1 A4” as both input and output instrument: by an iterative process, the user can find a spectral model that reproduces the distribution of counts in different bands. Then switch to a different output instrument (in terms of energy range, LED matches the higher end of XTE PCA and the lower end of XTE HEXTE) keeping that model.

For the A1 instruments, effective area curves for two gain settings, AGCL and AGCP. Both are normalized to produce count rates per square cm to allow direct comparison with HEAO-1 A1 X-ray Source Catalog (Wood et al. 1984, ApJSupp, 56, 507; also available online). The AGCP version is applicable to the majority of sources, while the AGCL setting is appropriate for sources at ecliptic longitudes in the 230-265 and 50-85 deg ranges (but excluding those at ecliptic latitude $> +80$ or < -80). The effective area curves were digitized from Fig. 7 of Wood et al. by Koji Mukai, while Dr. Kent Wood of NRL kindly provided additional information.

8.11 Hitomi

Hitomi (formerly *ASTRO-H*) is the Japanese-led international X-ray observatory with a substantial US contribution, and was launched on February 17th, 2016. PIMMS v4.8b contains effective area curves for the 4 instruments based on preliminary calibration available as of 2015 July. They will be updated with in-orbit calibration in the near future.

Soft X-ray Spectrometer (SXS) is an X-ray microcalorimeter based instrument located at the focus of an imaging soft X-ray telescope (SXT-S). We provide four files corresponding to the current set of science filters (open, 25 micron Be, and 50 micron Be, as well as the optical blocking filter, OBF). These files are appropriate for point sources on-axis, adding counts in all pixels of the 6x6 array. For the detector, a spectral resolution of 5 eV and the baseline set of XRS filters are assumed. For bright sources, SXS suffers from a photon pile-up effect: the fraction of events

that can be detected at the full resolution will decrease for higher count rate source. The current version provides a preliminary estimate of this effect, the accuracy of which is under investigation.

Soft X-ray Imager (SXI) is an CCD based instrument located at the focus of a soft X-ray telescope (SXT-I). The effective area curve is appropriate for a point source observed on-axis, analyzed with a 1.8 arcmin radius extraction region.

Hard X-ray Imager (HXI) is a CdTe imaging detector behind 4 Si layers. There are two units, each located at the focus of an imaging, multi-layer, hard X-ray telescope (HXT). The effective area curves are for one HXI unit for an on-axis point source with 1.8 arcmin extraction region. Two choices are offered for top layer only and for all layers.

Soft Gamma-ray Detector (SGD) is a narrow field-of-view Compton telescope operating in the 10-600 keV range. Its sensitivity at 300 keV is 10 times better than that of the Suzaku HXD. The current version provides preliminary estimates of the exposure times necessary for 3 and 5 σ detections with SGD, the accuracy of which is under investigation.

8.12 Integral

As of version 3.9f, PIMMS includes effective area curves for ISGRI and JEM-X instruments. See <https://www.isdc.unige.ch/integral/> for details of the mission. Since 2010 October, two units of JEM-X are operational, but PIMMS continues to provide count rate per one unit, based on calibration as of 2008 March. This is reflected in the mission-specific comments since PIMMS v4.3. based on calibration as of 2008 March.

In Version 4.11a, the ISGRI effective area curve was updated based on the latest calibration as of 2020 August.

8.13 IXPE

IXPE (Imagine X-ray Polarimetry Explorer) is a NASA small explorer (SMEX) mission with Italian participation to measure the linear polarization of celestial X-ray sources that was launched in 2021 December. As such, count rates as such are not of primary interest to IXPE users; PIMMS uses the predicted IXPE count rates to estimate, and display, the minimum detectable polarization (MDP) levels in percent for 10,000 s and 100,000s exposures. In fact, the users may be primarily interested in the exposure time necessary to reach a certain MDP level. For this purpose, the “go” command of IXPE allows an optional numerical parameter. If given, it will be taken the percent polarization of interest, and the exposure time needed to reach that MDP level will be calculated and displayed. See https://ixpe.msfc.nasa.gov/for_scientists/pimms/ for further details.

8.14 MAXI

MAXI (Monitor of All-sky X-ray Image) is an all-sky monitor on-board the International Space Station. MAXI payload includes two types of X-ray cameras, the Gas Slit Camera (GSC) and the Solid-state Slit Camera (SSC). PIMMS v4.7 contains effective area curve files provided by the MAXI team in mid-2013, normalized to produce count rates per square cm. More information on MAXI can be obtained from the MAXI home page at Riken (<http://maxi.riken.jp/top/>).

8.15 NICER

NICER (the Neutron star Interior Composition ExploreR) is a payload on the International Space Station for X-ray astrophysics. It achieves a high effective area, particularly in the 1 keV band, using a set of 56 concentrators, each with a dedicated silicon drift detector. Since NICER is not a true imaging instrument, PIMMS includes typical background rates and estimate times for 5σ detection (with just statistical errors and with an additional 10% systematic errors on the background) in the total NICER band as well as in two pre-defined energy ranges.

Note that the broadband background rate reported by PIMMS v4.9/v4.9a included background counts below 0.2 keV, where the rate is very high. This is outside the nominal energy range of NICER and resulted in more pessimistic estimates of the signal-to-noise than were appropriate. This has been corrected in v4.10.

The current (v4.11a) effective-area file were provided by the NICER project in 2020 August and is appropriate for preparation of Cycle 3 proposals.

8.16 NuSTAR

NuSTAR is an X-ray satellite with 10-meter focusing length and two side-by-side focal plane modules, each with 4 detectors. The count rate calculated by PIMMS reflects the total from both modules for a 50% PSF extraction region. In Version 4.7, the NuSTAR effective area curve file and related mission specific information were updated to reflect post-launch understanding, based on the response and background files for simulation released in 2013 August. For further details about this mission, see <http://www.nustar.caltech.edu/>

8.17 ROSAT

For the German XRT, effective area curve with PSPC (filter OPEN or BRN) and HRI are available. Also, beginning with v2.3, the Snowden R bands (see Snowden et al 1994, ApJ 424, 714) are available as software filters (R1, R1R2, R4, R4R5, R4TOR7, R5, R6, R6R7, and R7). For the British WFC, filters S1, S2, P1 and P2 effective area curves are available; these are appropriate for the time of launch. Note the S1 and S2 sensitivity dropped to $\sim 75\%$ of initial

value by the end of the survey, followed by a steeper decline to 15–20% of the original value after The Tumble. Non-survey (P1 and P2) filters have suffered much smaller degradation.

8.18 SAX

Although the official name for this Italian-Dutch satellite is now BeppoSAX, the mission name within PIMMS remains “SAX”. It was launched in Apr 1996 by an Atlas G-Centaur directly into a 600 km orbit at 3 degrees inclination. SAX carries 4 narrow field instruments (1 LECS, 2 MECS, 1 HPGSPC, 1 PDS), covering the energy band from 0.1 to 200 keV, and two Wide Field Cameras (WFC, 2-30 keV) which view the sky through a coded mask perpendicularly to the axis of the narrow field instruments. The LECS (0.1-10 keV) is an imaging gas scintillation proportional counter similar to the MECS but extends the energy range down to 0.1 keV. The MECS (1-10 keV) is an imaging gas scintillation proportional counter similar to the LECS. There are 2 working MECS on board SAX (a third unit developed a fault in May 1997). The count rate estimate is for the 2 MECS, starting with version 2.4b (previous versions estimated for 3 MECS). The HPGSPC is an high pressure gas scintillation proportional counter sensitive in the energy range 3-120 keV with a FOV of 1 deg. The PSD, phoswich detector system, consists in four phoswich units. The observations are carried out with two halves of the experiment alternatively pointing source and background region, providing a continuous monitoring of the background. The PSD is sensitive in the 15-300 keV energy bandwidth and has a FOV of 1.5 deg. The Wide field Cameras is position sensitive proportional counter sensitive in the 2-30 keV band. There are 2 WFC on board SAX. The FOV per unit is 20 deg X 20 deg with an angular resolution of a few arcmin.

8.19 Suzaku

Suzaku (formerly *Astro-E2*) is a Japanese-US X-ray astronomy satellite, launched in July 2005. The current PIMMS implementation is based on information from the instrument teams as of 2012 September for the HXD and 2014 December for the XIS, as collected by the Suzaku GOF (<http://suzaku.gsfc.nasa.gov/>).

Note, however, that AO-10 proposals must not require the HXD to achieve its core scientific objectives, as the satellite is operated without the HXD for the majority of time.

The Hard-Xray Detector (HXD) is a non-imaging instrument with an effective area of $\sim 300 \text{ cm}^2$ featuring a compound-eye configuration and an extremely low background. It consists of two types of sensors, silicon PIN diodes and GSO crystal scintillators.

Starting with v3.9h, PIMMS also outputs approximate time needed for 3-sigma and 5-sigma detections in standard energy bands (1 for PIN and 2 for GSO), taking into account the current level of systematic uncertainties in the background models.

There are four units of the X-ray Imaging Spectrometer (XIS) on-board *Suzaku*, three with frontside-illuminated (FI) CCDs and one with a backside-illuminated (BI) CCD, although XIS-2

(with an FI chip) has become inoperative in November, 2006. Each XIS detector is located at the focus of a conical foil X-Ray Telescope (XRT) with a 4.75m focal length. The CCD pixels of XIS vastly oversamples the XRT PSF, thereby allowing high S/N spectroscopy with a relatively benign amount of photon pile-up.

PIMMS currently returns count rate per one unit of XIS, with no further instrument specific information.

The X-Ray Spectrometer (XRS) lost its liquid helium cryogen and is no longer operational. A pre-launch estimate of the XRS effective area is included for reference.

8.20 Swift

Swift (see <http://heasarc.gsfc.nasa.gov/docs/swift/swiftsc.html>) is a multiwavelength gamma-ray burst observatory launched on 2004 November 20. Swift carries a wide-field (2 sr), coded-aperture Burst Alert Telescope (BAT, 15-150 keV); an X-Ray Telescope (XRT, 0.2-10 keV); and a UV/Optical Telescope (UVOT, 170-650 nm). The effective area curves for XRT now reflects the 2008 July CALDB release, for photon counting and window timing modes. The photodiode mode (no longer operative) is also included using an older calibration. Of the UVOT (9 filters, including “white” for unfiltered and 2 grisms) effective areas, those for the 2 grisms are pre-launch estimates, and others (in PIMMS 3.9f) are derived from the 2007 May CALDB release. The BAT response in PIMMS v3.6c and later yields the counts per fully illuminated detector, which matches the BAT analysis software default units. One detector has a geometric area of 0.16 cm². An on-axis source illuminates 16384 detectors; PIMMS v3.6b and earlier calculated the total on-axis count rates (i.e., per 16384 detectors).

Note that PIMMS is primarily an X-ray tool, and extrapolation to the UV regime introduces additional uncertainties. In particular, PIMMS assumes $E_{B-V} = N_H / 4.8 \times 10^{21}$ and an average Milkyway extinction law.

8.21 XMM

XMM-Newton (implemented using the pre-launch name, XMM, in PIMMS) was launched successfully in 1999 December. It consists of three coaligned high-throughput 7.5m focal length telescopes with six arc second (FWHM) angular resolution. The European Photon Imaging Camera (EPIC), which consists of two MOS and one PN CCD arrays, provide moderate spectral resolution over a 30 arc minute field of view. High-resolution spectral information ($E/dE \sim 300$) is provided by the Reflection Grating Spectrometer (RGS) that deflects half of the beam on two of the X-ray telescopes (those with the MOS arrays). The observatory also has a coaligned 30cm optical/UV telescope called the Optical Monitor (OM). See <https://www.cosmos.esa.int/web/xmm-newton> for further details.

The count rates for the EPIC MOS are given for one instrument each (we have averaged of MOS1 and MOS2 effective area curves), not for pairs of instruments. Starting with PIMMS v4.1, the

EPIC count rates are given for PATTERN=0–12 (MOS)/4 (pn) events over a large (5 arcmin) extraction region. This reverses the practice adopted in v3.6 to use a 15 arcse radius extraction region, and that adopted in v3.9c to report only the PATTERN=0 count rates for PN.

The count rates for the EPIC MOS are given for one instrument each (we have averaged of MOS1 and MOS2 effective area curves), not for pairs of instruments. Starting with PIMMS v4.1, the EPIC count rates are given for PATTERN=0-12 (for MOS)/PATTERN=0-4 (pn) events over a large (5 arcmin) extraction region. This reverses the practice adopted in v3.6 to use a 15 arcse radius extraction region, and that adopted in v3.9c to report only the PATTERN=0 count rates for PN. Starting with v4.11, PIMMS no longer provides information on timing and burst options for PN if thin or medium filter is specified, reflecting the new policy by the project. These options continue to be supported for PN observations only when using the thick filter.

For the RGS, count rates in RGS1 and RGS2 in two orders can be calculated separately (i.e., a total of 4 possible combinations). Even though the term “filter” is used (because that’s what the most common use of the third level of instrument specification in PIMMS), these do not represent physical filters. Data are taken in all three orders simultaneously, to be extracted into separate spectra using software filters.

For the OM, we provide effective area curves derived from the version 2.0 response files provided at the ESA site (<https://www.cosmos.esa.int/web/xmm-newton/om-response-files>).

Current version of PIMMS contains effective area curves appropriate for AO-20 proposals.

8.22 XTE

XTE, which was launched in Dec 1995, carries the All-Sky Monitor (ASM), large area proportional counter array (PCA) and the high energy X-ray Timing Experiment (HEXTE).

PCA is a mechanically-collimated array of five xenon proportional counter units (PCUs) with a total effective area of $\sim 7000 \text{ cm}^2$; however, different observations are taken with different numbers of PCUs on. Therefore, starting with PIMMS v2.7, user must supply the count rate *per PCU* when this is used as the input mission (‘from xte pca’). When used as the output mission (‘inst xte pca’), the first output is count rate per PCU summed over all energies and over all 3 xenon layers. Additional outputs (the rates in the 6 canonical PCA channels required on the proposal form and used in RECOMMEND) are given for 3 and 2 PCU combinations, which are becoming more frequent (and the proposal form requires numbers for 3 PCUs). The effective area curves, channel boundaries and the estimated background rates are all appropriate for ‘Epoch 4’ gain setting.

HEXTE consists of two clusters of detectors, with 4 scintillation detectors in each cluster. Count rates are given per cluster. Values are given for the total count rate, and the count rates in the 4 canonical HEXTE channels required on the proposal form and used in HEXTEmporize.

The quoted detection times assume two-cluster 16-s source/background beamswitching, i.e., one

cluster measures background while the other is on-source. In this case, the “detection time” applies to the combined HEXTE instrument. For those bright source observations (source rate \gg background rate) where a HEXTE cluster is selected to be in STARE mode, this detection time can also be interpreted as appropriate for a single HEXTE cluster. For the combined HEXTE detection time, divide by $\sqrt{2}$.

8.23 Flux

PIMMS can also calculate conversion to/from flux values not folded through any instrument responses can also be used. To use flux, the unit must be specified: “ERGS” for $\text{ergs cm}^{-2} \text{s}^{-1}$ or “PHOTONS” for $\text{photons cm}^{-2} \text{s}^{-1}$. Also necessary is the energy range of interest, to be specified in the form “2.5–10” (for 2.5 to 10 keV; PIMMS now accepts “2.0-20 A” to mean 2 to 20A range in wavelength). Optional keyword “UNABSORBED” following the range will make PIMMS calculate flux with Nh set to 0.0; this is useful in relating the flux to the total bolometric luminosity of the X-ray source before interstellar absorption.

8.24 (Flux) Density

New in PIMMS v3.3: it can now convert to/from flux density at a specific energy, rather than integrated flux over a range of energies (“flux”). To use density, the unit must be specified: “ERGS” for $\text{ergs cm}^{-2} \text{s}^{-1} \text{keV}^{-1}$ or “PHOTONS” for $\text{photons cm}^{-2} \text{s}^{-1} \text{keV}^{-1}$. Also necessary is the energy of interest (in keV). Alternatively, this can be specified as the wavelength in Angstroms, with the optional argument “Angstrom,” in which case flux density is in (photons or $\text{ergs cm}^{-2} \text{s}^{-1} \text{\AA}^{-1}$). Flux density can be “unabsorbed” as is flux.

8.25 Normalization

PIMMS also supports the use of ‘model normalization’. This is most useful for modelx imported from xspec, in which case a normalization of 1.0 is the flux level as simulated within xspec. The use of normalization is not recommended for models built-in to PIMMS, as they do not necessarily relate to any physical quantities.

9 User interface

9.1 Command interpreter

Commands can be abbreviated (as long as it is unique), numerical and character string parameters can be passed onto the commands. Parameters are interpreted according to their positions within the command line (first string is input file name, second file name is output file

name etc., although this does not happen in PIMMS). Some parameters are compulsory — PIMMS will prompt you for them if they are not given on the command line; others are optional (default values will be used unless the user specifies them on the command line). Commands can be stringed together by using a semicolon.

PIMMS can switch command input to a file, using <filename> convention. PIMMS will assume .xco extension, if none is given. Nested indirections are not allowed.

9.2 On-line help

PIMMS contains a VMS-style help facility, within which information is stored in a hierarchical structure. On the top level, there are two types of topics. Those listed in ALL CAPITAL LETTERS are PIMMS command names, containing the usage of these commands. Others are of more general nature, not linked with specific commands. HELP items are arranged in many levels, so that you start with a general introduction and pick up as many specific details as you like by going down several levels.

This help is case-insensitive (i.e., it accepts both lower-case and capital letters). If you type n characters, it will be matched against the first n characters of the topic names at that level. No wild card is allowed in specifying item names.

If the topic name string supplied by the user can be matched to (parts of) two more more topic names, then information on all the matching topics will be displayed.

Type “?” to repeat the current level.

Type <RETURN> as the topic name to go up one level.

To exit HELP, type the EOF character (␣ on VAX/VMS, ␣ on UNIX machines).

9.3 Spawn

Enter a dollar sign “\$” followed by a command to be spawned. Note that some operating system may not pass aliases, environment variables, logicals etc.

Appendix A PIMMS commands

A.1 MODEL

Command syntax: MODEL <name> <par> <nh> [<name> <par> <nh> <ratio> <refe>...]
or MODEL PL <par1> <par2> <par3> <nh>
or MODEL <filename> [<nh>]
or MODEL ?

Minimum abbreviation: M

Examples: “MO PL 1.7 3e21” “MO mymodel.dat”

Model specifies the spectral shape to be folded with the effective area curve of the instrument. Starting with version 3.0, up to 8 model components can be added together to represent multi-temperature plasma, power law plus Gaussian emission line, partial-covering absorber etc. Only a limited combinations of models have been rigorously tested; users of complicated models are urged to check the composite model by using the OUTPUT command.

As components, PIMMS recognizes BLACKBODY, POWERLAW, BREMSSTRAHLUNG, GAUSSIAN and PLASMA. If the model name string does not match these, PIMMS will try to interpret the string as a file name containing a precalculated model containing energy, photon flux pairs (see EXTERNAL_MODELS; MODELS_DIRECTORY). Nh, the equivalent neutral hydrogen column density (using Morrison & McCammon model) is expected for each component, except for GAUSSIAN and external files. Nh should be specified in full with an appropriate exponent (e.g., 2.5e21), or as a small non-zero number less than 30.0, to be interpreted as $\log_{10}(\text{Nh})$.

Model normalization for the built-in models do not necessarily correspond to physical quantities. Instead, PIMMS is designed to allow users to compare 2 observable quantities (count rates through specific instruments, or fluxes in specific energy bands) without having to know the model normalization.

Optionally, all components may be redshifted using a common z (in which case, all component Nh are interpreted as intrinsic absorber, with the same z) with an optional Galactic NH.

A.1.1 Syntax

The Model commands takes 1–8 blocks of component specification, and a final optional block of redshift specification. Each block starts with a valid name of a component (including a valid file name), followed by a set of numerical parameters. As a special case, the plasma model takes an optional string (‘logt’ or ‘kev’, the latter being the default) specifying the unit of temperature, immediately after the numerical parameter for the temperature. For 2nd through 8th component blocks, additional parameter(s) specifying the ratio of that component to component 1, and the reference energy at which this is to be evaluated, must also be given (NB the reference energy for Gaussian is always its central energy).

A.1.2 MODEL — ?

MODEL command with a question mark (or no parameters) will return a short listing of available models.

A.1.3 MODEL — Blackbody

Can be abbreviated to “BL..” or “BB”. Parameter is temperature in keV.

A.1.4 MODEL — Bremsstrahlung

Can be abbreviated to “BR..” or “TB” (short for Thermal Bremsstrahlung); the model include the Gaunt factor. Parameter is temperature in keV.

A.1.5 MODEL — Power Law

Can be abbreviated to “P..” or “PL”. Parameter is photon index (flux in $\text{photons cm}^{-2} \text{s}^{-1}$ is $E^{-(index)}$). You can now enter a negative number as the index, and PIMMS will calculate a power law that increases with increasing energy in photon space.

A power law with high energy cutoff $E^{-index} \exp[(E_{cut}-E)/E_{fold}]$ can be specified by typing “model pl 1.5 13.5 20.0 1e22” for example — this will result in an index of 1.5, cut-off energy of 13.5 and e-folding energy of 20 keV, with an N_H of 1E22.

A.1.6 MODEL — Plasma

Can be abbreviated to “PLA...”. PIMMS relies on grids of pre-calculated files, using the APEC (default), mekal, and Raymond-Smith codes. PIMMS v4.0 is distributed with APEC and Raymond-Smith models at 59 temperature ($\log T$ of 5.60 to 8.50 in an increment of 0.05) times 5 abundance (0.2 to 1.0 in an increment of 0.2), while mekal has a narrower temperature range starting with $\log T$ of 6.0 (51 temperatures to $\log T=8.50$). The syntax is “model plasma kT_Z j_{abun}_Z j_{nh}_Z ” (e.g., “model plasma 3.5 0.8 3e20”). The temperature can be specified in $\log T$ as adding the word “logt” after the first numerical parameter, which is then taken to be $\log T$. Starting in V4.7, APEC model files calculated using ATOMDB version 2.0.2 in XSPEC version 12.8.1g on 2013 Dec 9-11, assuming the solar abundances due to Asplund M et al. 2009, ARAA, 47, 481, are included. Between V4.0 and V4.6b, APEC files generated using ATOMDB 1.3.1 assuming Anders & Grevesse were included. Current mekal model files also assume Anders & Grevesse solar abundances, while the solar standard for the Raymond-Smith grid has become unclear due to passage of time. PIMMS will select the nearest temperature and abundance that is supported by the grid in use.

At start-up, the plasma model in use is APEC. The alternatives can be selected by issuing the PLASMA command.

A.1.7 MODEL — Gaussian

Can be abbreviated to “G”. This model takes the central energy and physical width (in keV) as parameters, and optionally also N_H . A physical width of 0 is allowed, which is interpreted as a delta function (integrations of delta function is treated appropriately, although it may look incorrect in the differential form, which is what is saved by the OUTPUT command).

Gaussian is primarily intended as second (etc.) component in addition to a continuum model, with the same N_H as the primary component. In such cases, specify the equivalent width in eV rather than the ‘relative strength’.

A.1.8 MODEL — External Models

Other, perhaps more complex, models can be imported in the form of an Ascii file containing energy (keV) vs. flux (photons $\text{cm}^{-2} \text{s}^{-1} \text{keV}^{-1}$ pairs. N_H correction is optional (i.e., interstellar absorption can be included when producing the file or done within PIMMS). If the full directory/file name is not specified, user’s current default directory is assumed first, and if not the models directory is searched.

A.1.9 MODEL — Models directory

Some external models (see help item under that name) may be kept under the MODELS subdirectory. If the file names and a short description is also included in the MODEL.IDX file, then PIMMS users will be able to see what is available.

A.1.10 MODEL — Importing from XSPEC

To import a model from XSPEC, start XSPEC and read, e.g., a template ASCA SIS pha file (which specifies the SIS response matrix which specifies the PHA channel boundary etc.). Create your model. Then use IPLOT MODEL command to plot the model, then from within plot use the WD <filename> command to output the model into an Ascii file. The program XSING within the MODELS directory should be used to convert the XSPEC output into a form readable by PIMMS.

A.2 ABSORPTION

Command syntax: ABSORPTION morrison-mccammon/mm/tubingen/tb

Minimum abbreviation: A

Example: “ABSORPTION MM”

This command specifies the X-ray absorption model to use. The default, chosen at start-up, is Tubingen (or TB), which is an approximation of the ttab model in xspec with the “wilm” abundances. This is meant to replace the old model which approximated Morrison-McCammon (MM). The two differ in terms of both cross sections and abundances, and can result in differences in PIMMS estimates of about 10%.

The ABSORPTION command is primarily intended to facilitate testing; in normal usage, the default (the Tubingen model) should be used.

A.3 PLASMA

Command syntax: PLASMA apec/mekal/rs

Minimum abbreviation: P

Example: “PLASMA MEKAL”

This command specifies the grid to use when the plasma model is specified. The default, chosen at start-up, is APEC. If a plasma model is currently in use (including as a component of a compound model), the grid is switched on the fly if at all possible. If none is being use, this command serves as a preliminary step for the next MODEL command that does include a plasma component.

A.4 FROM

Command syntax: FROM <mission> [<det> [<filt>]] [<lo>-<hi>]

FROM FLUX <unit> <lo>-<hi> [UNABSORBED] [ANGSTROMS]

FROM NORMALIZATION

Minimum abbreviation: F

Examples: “FROM EINSTEIN IPC” “FROM FLUX PHOTONS 0.5-10”

This command specifies the default “instrument” that the conversion is to take place from. This default will be used in GO (in count rate simulation mode) or POINT (in image simulation mode) command if not explicitly specified. See Missions for details of the available instruments, or try DIRECTORY. Initially the default is 2.0–10.0 flux in $\text{ergs cm}^{-2} \text{s}^{-1}$.

A.5 INSTRUMENT

Command syntax: INSTRUMENT <mssn> [<det> [<filt>]] [<lo>-<hi>]
or INSTRUMENT FLUX <unit> <lo>-<hi> [UNABSORBED] [ANGSTROMS]

Minimum abbreviation: I

Examples: “INST EXOSAT LE LX3” “INST FLUX ERGS 1-10 U”

This command specifies the “instrument” that the conversion is to take place to. See Missions for details of the available instruments, or try DIRECTORY. Initially default is ASCA SIS.

A.6 GO

Minimum abbreviation: G

Command syntax: GO <input_rate> [<mission> [<det> [<filt>]]] [<lo>-<hi>]
or GO <input_rate> [FLUX <unit> <lo>-<hi> [UNABSORBED]]

Examples: “G 1.0” “GO 3.4 EINSTEIN IPC”

This command actually tells PIMMS to execute the simulation.

Given a source spectrum in the form specified with MODEL, which produces an input rate (count rate in the specified instruments or flux) of <input_rate> it GO predicts what the rate would be for the instrument specified with the INSTRUMENT command. Unit of input rate can be specified here, or else the default is used (see FROM).

A.7 OUTPUT

Command syntax: OUTPUT <filename> <loE> <hiE> <deltaE>

Example: “OUT compoite 0.1 10.0 0.005”

This command produces an Ascii file containing the current spectral model, and is intended primarily as a debugging tool for complicated multi-component models. Each row consists of energy, total model flux, and flux of each component if there are more than one. The energy grid should be specified using the minimum and maximum values and the increment.

PIMMS currently forces output file names to be all lowercase.

A.8 SHOW

Command syntax: SHOW

Minimum abbreviation: SH

Presents a summary of the current defaults on the screen.

A.9 DIRECTORY

Command syntax: DIRECTORY [<mission> [<detector>]]

Minimum abbreviation: D

Examples: "DIR" "DIRE EXOSAT"

This command prints, on your screen, the full listing of missions that PIMMS recognizes. For explanations and comments, see "Missions" in this help.

A.10 LOG

Command syntax: LOG <log-file-name> or LOG close

Minimum abbreviation: L

Example: "LOG crab"

When this command is issued, PIMMS opens a log file (default extension .log). Thereafter, screen outputs from PIMMS (except for questions/prompts) will be copied to the log file. LOG CLOSE will close the current log file; the purpose of this command would be to send further output to a separate log file. This command will indicate error if (1) a log file is already open; (2) (on UNIX systems) the specified file already exists; (3) (on VMS systems) when the specified "log file name" is also a DCL Logical; and (4) PIMMS failed to open the file for the usual reasons, including a lack of disk space and file system protection.

PIMMS currently forces output file names to be all lowercase.

Appendix B Older Updates

B.1 New in v3.9/3.9a/3.9b/3.9c/3.9d/3.9e/3.9f/3.9g/3.9h/3.9i/3.9j/3.9k

Version 3.9k incorporates an updated set of effective area curves, as well as HXD background numbers, for Suzaku, suitable for Cycle 5 proposers.

Version 3.9j incorporates a new set of effective area curves for Chandra, suitable for use in writing Cycle 11 proposals.

Version 3.9i correctly treats the statistical errors in the Suzaku HXD background files provided to the users. Previous versions would have underestimated the necessary exposure times somewhat. It also corrects bugs for Swift XRT grade 0 count rates as well as ASCA count rates within the typical extraction regions, in cases when a limited energy range is specified. Also updated is the message regarding the instrument-specific extra information (or the lack thereof) when a limited energy range is specified.

Version 3.9h includes minor updates to the effective area curves for Suzaku XIS and HXD instruments. In addition, PIMMS now outputs approximate time needed for 3-sigma and 5-sigma detection in standard HXD energy bands (1 for PIN and 2 for GSO), given the current level of systematic uncertainties in the background models.

Version 3.9g includes updated effective area curves for XMM-Newton EPIC MOS cameras, with an added warning from the team regarding MOS1 timing mode data. It also includes updated effective area curves for Swift XRT.

Version 3.9f includes updated effective area curves for Constellation-X instruments (under the revised mission name, “conx”), XEUS, INTEGRAL (ISGRI and JEM-X), and for Swift UVOT (except grisms).

Version 3.9e includes updated effective area curves for the Chandra instruments for Cycle 10 proposers.

Version 3.9d includes updated effective area curves for Suzaku XIS and HXD instruments for Cycle 3 proposers.

Version 3.9c includes updated effective area curves for XMM-Newton EPIC instruments for AO-7 proposers. The major change is that, starting with this version, the PN count rates are given for PATTERN=0 events only, to be conservative. This will reduce the predicted count rates by about a third, depending on the spectral shape. Pile-up calculation has been adjusted to still use the total count rates.

Version 3.9b includes a bug fix for energy flux calculations using redshifted table-based models (including Raymond-Smith). Effective area curves for Chandra instruments have been updated for Cycle 9 proposers in v3.9b.

Effective area curves for Suzaku XIS and HXD instruments have been updated for Cycle 2 proposers in v3.9a.

Effective area curves for XMM-Newton EPIC instruments have been updated for AO-6 proposers.

One bug, which caused crashes for the command-line version on Linux platforms, has been fixed in this version.

B.2 New in v3.8/3.8a

The Swift/XRT effective area curves for Photon Counting and Windowed Timing data have been updated in v3.8a.

Previous versions used an old and incorrect deadtime fraction for burst mode for *XMM-Newton* EPIC-pn detector. This has been corrected.

With this version, PIMMS now calculates Swift/BAT count rates in 4 standard survey bands, and also includes the background count rates and hence the exposure time necessary to reach a signal-to-noise ratio of 5.0.

B.3 New in v3.7/v3.7a

Suzaku-specific information has been updated in v3.7a, with in-orbit calibration as of early November, 2005.

This version now provides assumptions regarding the input count rate (such as extraction region for imaging instruments) for various missions.

This version includes the AO-5 versions of *XMM-Newton* EPIC effective area curves, which differs slightly from the AO-4 versions. There are no updates for the RGS effective area.

This version also includes calibration updates of the *RXTE* PCA effective area curves. The count rate should increase by about 11% to previous versions. This is deemed minor enough that no impact is expected in proposals and in observation planning.

PIMMS now uses the post-launch name, *Suzaku*, for the former *Astro-E2*.

This version also includes post-launch calibration of the Swift XRT, in three data modes (photon counting, photodiode, and windowed timing).

B.4 New in v3.6/v3.6a/v3.6b/v3.6c

This version has the new Swift BAT effective area curve for one detector, to match the default units used in BAT analysis software. In comparison, previous versions (v3.6b and earlier) used the effective area for 16384 detectors (the total number fully illuminated by an on-axis source).

V3.6b differs from v3.6a in that it incorporates the new set of Chandra effective area curves for Cycle 7 proposers.

V3.6a differs from v3.6 in that it includes a new set of effective area curves for *XMM-Newton* RGS.

This version includes updated *XMM-Newton* effective area curves appropriate for AO-4 proposals. Note that, starting this version, the EPIC effective area curves are given for a 15 arcsec radius extraction region, which is typical for a point source. On-axis observation is assumed.

It also corrects a bug in model parser, and now allows specification of N_H for file-based models used as second (etc.) component.

B.5 New in v3.5

This version includes *Astro-E2* effective areas, based on best available calibration data as of 2004 July, and a routine to estimate XRS grade fractions for bright sources.

B.6 New in v3.4/v3.4a

V3.4a differs from v3.4 only in having an updated set of Chandra effective area curves for AO-6 proposers.

Swift effective area curves are newly included; to enable UVOT count rate predictions, a new UV/optical extinction function has been added to the code.

B.7 New in v3.3/v3.3a

PIMMS now allows to convert to/from flux density; it can be in $\text{photons cm}^{-2}\text{s}^{-1}\text{keV}^{-1}$, $\text{ergs cm}^{-2}\text{s}^{-1}\text{keV}^{-1}$, $\text{photons cm}^{-2}\text{s}^{-1}\text{\AA}^{-1}$, or $\text{ergs cm}^{-2}\text{s}^{-1}\text{\AA}^{-1}$ depending on whether the energy/wavelength is specified as keV or in \AA .

V3.3 also incorporates *Chandra* updates for Cycle 5.

V3.3a incorporates *XMM-Newton* effective area curves for AO-3 proposers.

B.8 New in v3.2/3.2a/3.2b/3.2c/3.2d

Chandra effective area curves have been updated in V3.2d for Cycle 4 proposers. In addition, it corrects a minor bug in `pms_slmdl.f` (the bug caused PIMMS to run out of memory unnecessarily when repeatedly reading in file-based spectral models), and another in `pms_rarea.f` (this bug prevented PIMMS from reading effective area curve of the maximum specified size).

V3.2c corrects one bug introduced in 3.2a (3.2b was an attempt to correct this, but it was only partially successful); if 3.2a or 3.2b crashes, obtain either 3.2c or just one corrected file, `pms_docrt.f`. (The XTE HEXTE effective area curves have also been updated in 3.2c, but this should not have a major effect on the calculations.)

V3.2a incorporates cosmetic tweaks to eliminate unnecessary warning messages.

1. XMM-Newton AO-2 support: Effective area curves for EPIC-MOS, EPIC-PN, and RGS have been updated using in-orbit calibration.
2. Also includes a new formula to estimate pile-up for EPIC-MOS, based on in-orbit data.
3. WARNING: This version does not have an updated pile-up formula for EPIC-PN.

B.9 New and updated in v3.1a/3.1b/3.1c

1. Bug fix in 3.1c: Multiple component models with two or more Raymond-Smith models now work correctly.
2. Chandra AO-3 support, including clarification of first order count rates.
3. Minor clean-ups and bug fixes of v3.0.

B.10 New and updated in v3.0

1. Chandra AO-2 support.
2. Preliminary Integral support, including CGRO OSSE effective area curve.
3. Multi-component model capability.
4. Capability to read commands from a file using `@<filename>` syntax.

B.10.1 New and updated in v2.7

1. Latest (1999 June) effective area curves for the ASTRO-E instruments.
2. Now uses XTE PCA count rate per PCU (Proportional Counter Unit), not per 5 PCUs.

3. Changed all (except historical) references to ‘AXAF’ to ‘Chandra’.
4. Enlarged the buffer size for storing external spectral models (supplied as an ASCII file) to 65536 lines.

B.11 New and updated in v2.6 through v2.6c

1. 1999 January versions of ASTRO-E XRS and XIS responses, including the XRS event grade calculations.
2. 1999 January versions of XMM EPIC responses, including the pile-up and dead-time calculations.
3. RXTE PCA calibrations appropriate for ‘Epoch 4’ gain setting.

B.12 New and updated in v2.5

1. β -release support for AXAF ACIS pile-up calculations.
2. Whenever energy range can be/must be specified, wavelength range (in \AA) can be specified instead.
3. Restrictions on power law index has been eliminated.
4. First preliminary effective area curves for ASTRO-E XRS is included.

B.13 New and updated in v2.4b

1. Updated calibrations of the SAX instruments.
2. Bug-fix for long path/file names

B.14 New and updated in v2.4

1. Updated calibrations of the XTE instruments for AO-3 proposals.
2. New ASCA SIS telemetry limit calculations based on the latest hot/flickering pixel rates.
3. Pimms now supported on Linux machines with g77, on a beta-test basis.
4. Model normalization can be used as input rate.

B.15 New and updated in v2.3

1. New (in-orbit) calibrations for XTE PCA and HEXTE instruments. Use of the new numbers is a requirement for XTE AO-2 proposals.
2. An optional set of extra Raymond-Smith models, suitable in particular for EUVE and ROSAT data.
3. The “Snowden R-band” effective area curve, courtesy Dr. Richard West of Leicester.
4. A new command “LOG”: this allows users to capture PIMMS output in a log file.